Wilco Airbus Software Module for VRInsight CDU II

No mouse click generation, no need to store flight files, no FSUIPC required...

This software is intended to have the VRInsight CDU II working seamlessly with the Wilco Airbus Series Volume 1 and Volume 2. VRInsight already provides all the necessary software to have the CDU II working with the Wilco Airbus Series, so why is this software different?

Here is the answer:

- No mouse click generation: The VRInsight software emulates the MCDU key presses by generating mouse clicks at specific coordinates. If the MCDU II-Keypad window is not correctly positioned, the mouse clicks are not generated at the right coordinates and it fails. My software works directly with the MCDU gauge without needing any mouse click generation. It is easier and works all the time, whatever the window positions and screen configuration.
- Only 1 MCDU window: When you install the CDU II with the VRInsight installer, it updates the Wilco Airbus panels so that 2 MCDU panel windows are created: MCDU II-Display (for the screen) and MCDU II-Keypad (for the MCDU keys). Having 2 MCDU screens displayed at the same time can cause problems, one of them sometimes disappears. With my software, only the MCDU II-Display window is needed, no more display problems.
- Full Screen: Even though FS2004 must run in windowed mode to allow the placement of the MCDU screen on the CDU II, my software lets you see FS2004 in full screen.
- Full FS Integration: My software is fully integrated within FS2004/FSX. Every function is accessible within the sim itself through a window-based interface or through predefined key presses.
- Immediate Access: My software stores the MCDU screen position so that it fits the CDU II screen. It can be restored at any time without requiring the selection of a flight. Load the aircraft you want, as you wish, and have the MCDU screen correctly displayed just by a single key press.
- My software does not require FSUIPC.

How does it work?

First, you must follow the VRInsight installation procedure which installs the hardware device driver (USB Serial Converter), installs the necessary software (especially Serial FP2) and updates the Wilco Airbus panels as required. Follow all the VRInsight procedure to configure the monitors correctly and set up the panels, as explained in the CDU II documentation.

CDU II panel USER MANUAL (MEG2 586-390CT988)	Masker wet log 1. Oach frauwer fairbag proporties in order full anather sub-monton's connected ar vol. (See "Selfigh")	EVERYTHE REAL AND A DECEMBER OF A DECEM
Please real this massed before operating your units and keep it for future reference.	Connect while width of COUII to your compute: Connect width of COUII to your COUI: Connect width of COUII to your COUII Count of the COUII to width of the COUI	 Version and the second s
VRinzight		Type and/or a many part. You's first of the state of
All stated has in subject to change etilized observed notice for large maximum. No obstation of no observations and <u>any property on the one one magnetice</u>	T	

When this is done, you can load any Wilco Airbus aircraft. The 2D panel appears with 2 new windows visible: the MCDU II-Display that shows only the MCDU screen and the MCDU II-Keypad that shows the whole MCDU.

You can hide the second window MCDU II-Keypad, it is now useless.

Unlike what is written in the VRInsight documentation, you **must not** run the Serial FP2 utility. Now you will start using the Wilco Airbus CDU II software.

First time

The first time you use this software, you should see something like this:



Now follow these steps:

- 1. Close the MCDU-II Keypad window, it is now useless. It should not appear next time you select this aircraft.
- 2. Undock the MCDU-II Display window
- 3. Press the key that displays the main menu (Ctrl-F8 by default)
- Click the button labeled "Show Panel Position Assistant" or press Ctrl-F11 (default key). The panel position assistant appears to let you position

and resize the MCDU screen accurately so that it fits the CDU II screen. The arrow set on the left lets you move the window quickly or accurately, and the right part lets you change its width and height to size it accurately.

The optimal positioning is when the Left/Right Select Keys are in front of the lines displayed on the screen. Don't forget to keep some space for the title (top) and for the scratchpad (bottom).

5. When the window is properly positioned, press the button labeled "Store Current MCDU position" or press Ctrl-F9 (default key). At this time, the window positioned is stored and will be reused each time you fly a Wilco Airbus aircraft, you will not have to position it again.



6. That's it, you can close the window.

Next times...

Next time you want to use the CDU II with a Wilco Airbus aircraft, the MCDU window may be correctly positioned. If not, do the following:

- 1. Undock the MCDU-II Display window. You don't have to care about the window position and size.
- 2. Open the software main menu (Ctrl-F8 by default)
- 3. Click the button "Restore MCDU in CDU II
- 4. That's it, you CDU II is ready to work with the Wilco Airbus MCDU

Instead of steps 2 and 3, you can also press the key associated with this function (Ctrl-F10 by default)

Full Screen Feature

In order to take advantage of the full screen feature offered by this software, follow these steps:

1. Configure the Windows taskbar in "auto-hide" mode so that it does not appear at the bottom of the screen.

- 2. Configure FS (FS2004 or FSX) to hide the menu bar:
 - FS2004: right click and select "Hide Menu bar"
 - FSX: press ALT key for a few seconds
- 3. Open the main menu and click the button labeled "Show/Hide FS Main Window Border" or press the key associated to this function (Ctrl-F12 by default)

With no taskbar, no menu bar, no title bar and no border, the main FS window takes all the space on the screen.

Configuration Utility

All the functions of this software are accessible through single key presses. By default, they are defined as shown here:

Ctrl-F8	Show Main Menu
Ctrl-F9	Store current MCDU position
Ctrl-F10	Restore MCDU in CDU II
Ctrl-F11	Show panel position assistant
Ctrl-F12	Show/hide FS main window border

You can change the key assignment by running the configuration application.

🏙 CDU2 for Airbus -	Configuration	X
Keys		
Select a <u>C</u> ommand	Show CDU II Main Menu	
Current Key	CTRL + F8 Change Key	
	Reset Default Keys	
COM Port (Optional)		_
If you know the COM only if you experience	port used by your CDU II, you can select it here. Use this option conflicts with other hardware devices.	1
СОМ	Unknown	
Save	Save & Close Close	

In the "Keys" section, select a command, the associated key appears below. Click "Change" if you want to change the key. A new window appears to let you define another key.

B CDU2 for Airbus	- Configuration	X
Keys		
Select a <u>C</u> ommand	Show CDU II Main Menu	~
	Key Selection	
Current Key	Select a key for this command and press OK to validate	Shange Key
	CTRL + MAJ + M	
- COM Port (Optional) -		
If you know the C(only if you experie	OK Cancel	re. Use this option
COM	Ontherm [1]	1
Save	Save & Close	Close

Press the key that you want to assign or leave "None" if you want to have no key defined.

The configuration utility also lets you specify the COM port number used by the CDU II. Use this feature only if you have a conflict with another hardware device controlled by a COM port. If not, just leave it as "Unknown" and the software will find the CDU II automatically.

If you have to specify the COM port number, you can easily find it with the device manager.

🗏 Gestion de l'ordinateur		
📕 Eichier <u>A</u> ction Aff <u>i</u> chage Fenê <u>t</u> re	2	_ B ×
🖳 Gestion de l'ordinateur (local)	🗄 🥪 Lecteurs de disque	^
🚊 🖺 Outils système	🗄 🤳 Lecteurs de disquettes	
🕀 🗊 Observateur d'événements	🗄 📲 Moniteurs	
🕀 👰 Dossiers partagés	🗄 🖳 😼 Ordinateur	
🕀 🔝 Utilisateurs et groupes locau:	🗉 🖾 Périphériques d'interface utilisateur (HID)	
🕀 🎆 Journaux et alertes de perfo	🗄 🖳 😼 Périphériques système	
Gestionnaire de périphérique	🖃 🖉 Ports (COM et LPT)	
🖻 🊈 Stockage	Port de communication (COM1)	
🕀 🚔 Stockage amovible	USB Serial Port (COM5)	
Défragmenteur de disque	USB Serial Port (COM7)	=
Gestion des disques	🗉 🚓 Processeurs	
主 🙀 Services et applications	🗄 🕛 Souris et autres périphériques de pointage	
<	主 🥪 Volumes de stockage	~

As shown on this example (my personal configuration), you can see I use a CPFlight FCU, which had a conflict with the VRInsight CDU II. Looking at the device manager, I could see the FCU uses the COM port #5, whereas the CDU II uses COM port #7. In this case, I just had to specify the port #7 in the configuration utility and all conflicts were resolved.

Registration

At the end of the installation process, you are asked to enter your email address and your key to proceed to registration. If you don't have a key at this time, you can use this software for 10 days (trial period).

If you purchase a key, you can register it later by running the registration application. </br>

You can enter your email address and the key that was provided to you when you purchased the software.

ᡖ CDU2 for Airbus	- Register 🛛 🔀	
Registration Please enter your r	egistration information:	
E-mail Address		
Кеу		
If you do not have a registration key yet, just press Cancel. You will have a trial version during 10 days after the installation.		
ОК	Cancel	

Please copy and paste the key to avoid any error when entering it (a confusion between 0 and 0 is so easy...)

If the registration is successful, a message appears to confirm this.